

## MPC4000 V1.71 Software Release Notes

MPC4000 V1.71 has been released with the following bug fixes from V1.70.

### **[Bugs fixed]**

1. Crash when deleting sequences in SONG page in certain circumstances.
2. In the SONG page, continually copying & pasting a 999Bar sequence could cause a crash.
3. Slow behavior of EDIT PROGRAM page during the sequence playback (with using Internal voices).
4. There was no EJECT button in the MEMORY TO CD function screen.
5. St/End point of the sample made by S5/6000 cannot be correctly loaded.
6. E-MU format sample cannot be correctly loaded.
7. When performing DELETE SECTION of a sample, if the section selected was the full length of the sample, a zero-length sample could be created (it had no audio data). In version 1.71, this now displays "This process cannot be completed as the resultant sample will be too small".
8. When Auto Load is set to "ON", startup with only one IDE device (HDD or CD-RW etc) is very long. The startup time in this situation has been improved.

### **[Note]**

O.S. V1.71 for MPC4000 will be uploaded on AKAI professional web-site.  
Addendum operator's manual for V1.71 will not be issued.

--- end of file---